

Installation Manual

BASIC REQUIREMENTS TO INSTALL SPECIFI SOFTWARE

To properly install the Specifi software it is necessary that your computer has one of the following operating systems:

Windows® 7 (SP1) - 64 bit (not recommended) Windows® 8, 8.1 - 64 bit Windows® 10 - 64 bit

Minimum requirements for Specifi Design (Specifi Design or Design+):

- CPU Processor: Intel® Quad Core® 2.8 GHz or Core i5, i7 2.6 GHz
- RAM: 8GB or more
- GPU: Dedicated Direct3D graphics card with minimum capacity 2GB (suggested GPU compatible with AutoCAD/Revit)
- 1280 x 1024 32-bit color video display adapter (True Color)
- 2GB of hard disk available not including libraries installation
- Display scaling settings (texts, icons, apps): 100%

Specifi Design is compatible with: AutoCAD from 2016 to 2020 (not LT version) Revit from 2016 to 2019 (not LT version) *(not required if you want to install Specifi Design+)*

Minimum requirements for Specifi Quote:

- Processor: Intel® Dual Core® 2.6 G or higher
- RAM: 4GB RAM or higher
- 1280 x 1024 32-bit color video display adapter (True Color)
- 2GB of hard disk available not including libraries installation
- Display scaling settings (texts, icons, apps): 100%

Before starting the installation, make sure you have **USERNAME** (usually your email) and **PASSWORD**, which you have been given to access to the reserved area of Specifi website.

In case you don't have these information, we kindly ask you to contact our Customer Service sending an email to <u>helpdesk@specifiglobal.com.</u>



10 SIMPLE STEPS TO INSTALL PROPERLY YOUR SPECIFI SOFTWARE

Through the link received, download and run the "setup_main_win.exe" file.

Sp Specifi™ Installer Setup	×
Extracting the main application files	

The setup will first check that system prerequisites are properly installed, otherwise it will assist in their installation.

Click on "Next" to proceed to the download and installation of the components.

At first, select the desired installation language and click Next.







4 Select Typical Installation and go to Step n°6. Choosing Typical the setup procedure Will install by default SPECIFI DESIGN (if a compatible CAD Engine has been previously installed) and SPECIFI QUOTE.

	Sp Specifi® Installer	-	×
⊘	Typical Installation		
③	Custom Installation		

If you need to install Specifi Design+ and Specifi Quote choose "Custom Installation", then select the following options and click "Next" button:

	Sp Specifi® Installer	-
	Select Select Select	
Back	All trademarks and logos belong to their respective owner	Next

If you want to install Specifi Server, we kindly recommend to contact Specifi Technical Support, sending an e-mail to <u>helpdesk@specifiglobal.com</u>.





Choosing "Custom Installation", you can set the configuration mode (Standalone/ Network) and the paths for Specifi main database, projects and libraries.

We suggest to do not change the default settings.

Sp Spec	ifi® Installer
Software	e configuration mode
Standalor	ne 🗌 Network Mode
DataBase Configuration	Paths Projects
	C:\Users\TESTuser\Documents\SpecifiProjects
DB Host/Path:	Images (Libraries)
C:\Users\Public\Roaming\SpecifiGlobal\Specifi\mcd	data C:\Users\Public\Roaming\SpecifiGlobal\Specifi\BRANDS
	DataBase (Libraries)
	C:\Users\Public\Roaming\SpecifiGlobal\Specifi\BRANDS\DB
Back	Install

Click "Install" button.

5 While installation process is running, the Specifi Installer downloads and installs the prerequisite software too.

Sp Specifi® Installer	- 0 X
Please wait while the Setup Wizard installs Specifi® Installer. This may take several minutes.	
Status: Downloading prerequisite software	

For instance, if you added the Specifi Design+ CAD engine, it will download and install automatically.



If you are installing Specifi DESIGN and your PC has more than one CAD engines installed, the following screen will be displayed. Then select the corresponding line to the CAD engine you want to use with Specifi and click on the "Next" button.

6

Installer				- 🗆 X					
Sp Specifi™ Installer									
Installation statu	JS								
t may take a while to instal	l Specifi™ on your co	omputer.							
				1.1.					
In order to proceed you m	ust select an item ar	nong the list of CA	D installations a	vailable on your computer.					
Software name		Version	Туре	Installation path					
AutoCAD 2019	ENU	x64	R23.0	C:\Program Files\Autodesk\AutoCAD 2019\acad.exe					
Bricscad	ENU	x64	V17	C:\Program Files\Bricsys\BricsCAD V17 en_US\bricscad.exe					
Sp Design+	ENU	x64	R23	C:\Program Files\Autodesk\Specifi Design+ 2019\SpCAD.exe					
Refresh									
				1					

7 Fill out the form with your username and password (received by our operator) and click the "Request" button to obtain the installation code and enable the Next button.

taller				-		×
	Sp Specifi™ Installe	er				
stallation status						
ay take a while to install Specifi™ on t	your computer.					
In order to proceed with the installati login). Please click on "Register" if you have r Keep in mind that the installation cod	on you wust insert both installation code and Specifi ¹²⁸ ID (als	so known as Liv	eupdate/www.m	lasterche	r-cad.cor	1
(!) If you already have an installation o "Request". Contact Name	obe for this computer please insert it below and click on "Che	eck" button to	validate the form,	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and surname	and software type computer and software type computer and software type computer please insert it below and click on "Che	eck" button to	validate the form,	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and slurname UserID (email) Your email address	Password Password Your password	eck" button to	validate the form,	, otherwi	se click o	n
(!) if you already have an installation o "Request". Contact Name Your name and slurname UserID (email) Your email address Installation code	Password Password Your password	eck" button to	validate the form, Register	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and slurname UserID (email) Your email address Installation code	Password Password Your password	cken button to	validate the form, Register	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and slurname UserID (email) Your email address Installation code Usually it matches the following patter	Password Password Your password rn: X0000000C-X0000000C-X0000000X	eck" button to Request	validate the form, Register	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and slurname UserID (email) Your email address Installation code	Password Password Your password rn: X0000000-300000000-300000000	eck" button to Request Check	validate the form, Register	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and slurname UserID (email) Your email address Installation code	Password Password Your password rn: X0000000-30000000-300000000	eck" button to '	validate the form, Register	, otherwi	se click o	n
(!) If you already have an installation o "Request". Contact Name Your name and surname UserID (email) Your email address Installation code Usually it matches the following patter	Password Password Your password rn: X0000000-X00000000-X00000000	eck" button to	Register	, otherwi	se click o	n

If your credentials are correct, a message will confirm you the successful creation of the installation code. Click "OK" and then on "Next" button.



Sp				- 🗆	×
	Se	nding the code re	equest		
START	COLLECT DATA	REGISTRATION STATUS	SENDING REQUEST	END	
Retry	atic code request procedure	completes successfully, just close ti	nis window and go on with setu	D	
		, , ,, ,	^	·	
	installa procee	tion code has been successfu d with installation now.	ully validated, you can		
			ОК		

8 Now Specifi database initialization procedure has started. Once it will finish, a confirmation message is displayed. Click on the "OK" button.

Sp	Installer Specifi™ Installer	-		×
	54 %			
	Software configuration has been successfully completed. Now setup will proceed with module installation packages automatically.	and this window t	will close	
	Cancel All trademarks and logos belong to their respective owners	Previous	Nex	

The Specifi Installer starts to download the installation package of product you choose.







Note: the MS-DOS window (black screen) could be opened as you can see below .

El\User\User\AppData\Local\Temp\CuttomActions_1.0.0\CuttomActions.exe	-	×
8 provider is updating itself: Database initialized		
B provider is updating itself: Verifying DB contents		
8 provider is updating itself: Verifying languages contents		
8 provider is updating itself: Verifying ContactCategories contents		
8 provider is updating itself: Verifying ApplicationTable contents		
8 provider is updating itself: Verifying Currencies contents		
8 provider is updating itself: Verifying Zones contents		
8 provider is updating itself: Verifying States contents		
B provider is updating itself: Verifying DocumentTypes contents		
8 provider is updating itself: Verifying Tags contents		
<pre>g provider is updating itself: Veritying Attachmentlypes contents</pre>		
s provider is updating itself: verifying ConnectionConstraints contents		
s provider is updating itself: verifying TycketTypes contents		
e provider is updating itself: verifying typeuoc contents		
e provider is updating itself: verifying val vertentage contents		
s provider is updating itself: verifying Petroprayment contents		
s provider is updating itself: weritying progressive serial number, activity, ficket code contents		
i provider as updating reserve de de de la content intrairieu		
illing a consume field for prize tables (may take for minuter)		
iling is component field for description tables (may take for minutes)		
illing is component field for accessories tables (may take few minutes).		
scenting recomposition take (mass rates over the second of		
nserting contract hack image substance		
nserting contract closing text category		
nserting contract dealer logo category		
nserting contract first page image category		
nserting contract footer category		
nserting contract header category		

Please do not take any action until the MS-DOS window is closed automatically at the end of the procedure.

The confirmation message informs you of the successful installation of Specifi.

		Sp Specifi Setup	×
Installation	×	Ð	Completing the Specifi Setup Wizard
Installation has been successfully completed.			Click the "Finish" button to exit the Setup Wizard.
ОК			
			Einish

Click the "Finish" button to close the installation process.



9



On your desktop, you will find 3 icons: Specifi (blue icon), Specifi LiveUpdate (white icon, SP-Connect (blue icon with headset).



The first one identifies the starting icon of your Specifi software



The second one allows you to download the libraries of authorized manufacturers and software updates.



The third one permits to run the remote connection with Specifi technical support.

Once the installation is completed, Specifi LiveUpdate starts automatically. Click on "Download - Update" button to download and install available updates.

Sp Specifi LiveU	odate		- [) ×
Sp	pecifi	LIVE	UPDA	ГЕ
Aggiornare	Storico Impostazioni			Home
Codice	Descrizione	Data	Size	VerMin ^
🗹 🚍 0339	2013GM			
	2013GM Database - Upgrade 4	15/10/2014	0,3 MB	
🗹]	2013GM ZERO PRICELIST	15/10/2014	2,3 MB	
🗹 🚍 0010	A.T.A. Srl			
	ATA S.r.I. DWG	04/04/2012	19,2 MB	4
🖂 🧰	ATA S.r.I. JPG	04/04/2012	6,0 MB	4
☑ 🔚	A.T.A. Srl DWG - Upgrade 13	13/10/2015	25,9 MB	5.3
🗹 🧫	A.T.A. Srl JPG - Upgrade 13	13/10/2015	8,7 MB	5.3
☑ 🔚	A.T.A. Srl DWG- Upgrade 15	09/12/2015	25,9 MB	
🗹 🧰	A.T.A. Srl JPG - Upgrade 15	09/12/2015	9,5 MB	
	A.T.A. Srl Database - Upgrade 16	15/02/2016	0,2 MB	5.3
🗹]	ATA ZERO PRICELIST	15/02/2016	0,6 MB	5.3
☑ 🔚	A.T.A. Srl DWG - Upgrade 17	11/04/2016	0,3 MB	5.3
🗹 \Xi 0399	Abat			
	Abat DWG - Upgrade 1	16/09/2015	9,2 MB	5.3
🖂 🧰	Abat JPG - Upgrade 1	16/09/2015	0,5 MB	5.3
🗹 🧰	Abat PDF - Upgrade 1	16/09/2015	2,5 MB	5.3
	Abat Database - Upgrade 3	12/01/2017	0,1 MB	5.3
	Abat DWG - Upgrade 3	12/01/2017	14,8 MB	5.3
🗹 🧫	Abat JPG - Upgrade 3	12/01/2017	2,4 MB	5.3
🗹]	ABAT RUBLES PRICELIST	12/01/2017	0,2 MB	5.3
🔽 😑 0202	Actri			Y
Connected as	s: m.rizzetto@specifiglobal.com		Scarica - Aggior	na

Click the button "Download - Update" on bottom right corner to install the available updates.



Sp Specifi LiveUpdate			- 0	×
Specifi	LIVE UPDATE			
Aggiornare Storico Impostazioni			Home	
Descrizione	Data	Upgrade [%]	Stato di avanzamento	î
🗹 🥪 2013GM Database - Upgrade 4	15/10/2014	100%	Downloaded	
🗹 🥪 2013GM ZERO PRICELIST	15/10/2014	100%	Downloaded	
🗹 🥪 ATA S.r.I. DWG	04/04/2012	100%	Downloaded	
🗹 🥪 ATA S.r.I. JPG	04/04/2012	100%	Downloaded	
🗹 🥪 A.T.A. Srl DWG - Upgrade 13	13/10/2015	100%	Downloaded	
🗹 🥪 A.T.A. Sri JPG - Upgrade 13	13/10/2015	100%	Downloaded	
🗹 🥪 A.T.A. Srl DWG- Upgrade 15	09/12/2015	100%	Downloaded	
🗹 🥪 A.T.A. Srl JPG - Upgrade 15	09/12/2015	100%	Downloaded	
🗹 🥪 A.T.A. Sri Database - Upgrade 16	15/02/2016	100%	Downloaded	
🗹 🥪 ATA ZERO PRICELIST	15/02/2016	100%	Downloaded	
🗹 🥪 A.T.A. Srl DWG - Upgrade 17	11/04/2016	100%	Downloaded	
🗹 🥪 Abat DWG 🛛 - Upgrade 1	16/09/2015	100%	Downloaded	
🗹 🥪 Abat JPG - Upgrade 1	16/09/2015	100%	Downloaded	
🗹 🥪 Abat PDF - Upgrade 1	16/09/2015	100%	Downloaded	
🗹 🥪 Abat Database - Upgrade 3	12/01/2017	100%	Downloaded	
🗹 🏟 Abat DWG - Upgrade 3	12/01/2017	49%	7410 of 15115	
🗹 🥪 Abat JPG - Upgrade 3	12/01/2017	100%	Downloaded	
🗹 🥪 ABAT RUBLES PRICELIST	12/01/2017	100%	Downloaded	
🗹 🤹 Acfri DWG - Upgrade 4	13/07/2018	28%	2248 of 8018	
🗹 🤖 Acfri JPG - Upgrade 4	13/07/2018	0%		_
🗹 🧰 Acfri PDF - Upgrade 4	13/07/2018	0%		

Sp Specifi LiveUpdate			- 0	×
Specifi	LIV	/E UP	DATE	
Aggiornare Storico Impostazioni			Home	
Descrizione	Data	Upgrade [%]	Stato di avanzamento	^
🗹 🥪 2013GM Database - Upgrade 4	15/10/2014	100%	Completed	
2013GM ZERO PRICELIST	15/10/2014	100%	Waiting	
🖂 🥪 ATA S.r.I. DWG	04/04/2012	100%	Completed	
🗹 🥪 ATA S.r.I. JPG	04/04/2012	100%	Completed	
🗹 🥪 A.T.A. Srl DWG - Upgrade 13	13/10/2015	100%	Completed	
🗹 🥪 A.T.A. Srl JPG - Upgrade 13	13/10/2015	100%	Completed	
🗹 🥪 A.T.A. Srl DWG- Upgrade 15	09/12/2015	100%	Completed	
🗹 🥪 A.T.A. Srl JPG - Upgrade 15	09/12/2015	100%	Completed	
🗹 🌄 A.T.A. Sri Database - Upgrade 16		44%		
ATA ZERO PRICELIST	15/02/2016	100%	Waiting	
A.T.A. Srl DWG - Upgrade 17	11/04/2016	100%	Waiting	
Abat DWG - Upgrade 1	16/09/2015	100%	Waiting	
Abat JPG - Upgrade 1	16/09/2015	100%	Waiting	
Abat PDF - Upgrade 1	16/09/2015	100%	Waiting	
Abat Database - Upgrade 3	12/01/2017	100%	Waiting	
Abat DWG - Upgrade 3	12/01/2017	100%	Waiting	
Abat JPG - Upgrade 3	12/01/2017	100%	Waiting	_
ABAT RUBLES PRICELIST	12/01/2017	100%	Waiting	
Acfri DWG - Upgrade 4	13/07/2018	100%	Waiting	_
Acfri JPG - Upgrade 4	13/07/2018	100%	Waiting	_
Acfri PDF - Upgrade 4	13/07/2018	100%	Waiting	~
Connected as: m.rizzetto@specifiglobal.com		Cancell	a aggiornamento	

Once the updates are installed, click the OK button.



You can start Specifi double clicking the blue icon on your desktop.



HOW TO UNINSTALL SPECIFI SOFTWARE

To uninstall the software, go to the Windows Control Panel, and click on "Programs and Features".

2 Select SpecifiSuite product, and click on the "Uninstall" button that appears at the top.

ograms and Features					-	
→ ↑ ▲ Control P.	anel > Programs > Programs and Features			~ Č	Search Programs ar	nd Features
introl Panel Home	Uninstall or change a program					
w installed updates	To uninstall a program, select it from the list and then	click Uninstall, Change, or Repair.				
rn Windows features on or						
F	Organize 👻 Uninstall Change					
	Name	Publisher	Installed On	Size	Version	
	Microsoft Visual C++ 2012 Redistributable (x64) - 11.0	Microsoft Corporation	3/6/2019	20.5 MB	11.0.61030.0	
	Microsoft Visual C++ 2012 Redistributable (x86) - 11.0	Microsoft Corporation	3/6/2019	17.3 MB	11.0.61030.0	
	Microsoft Visual C++ 2017 Redistributable (x64) - 14.1	Microsoft Corporation	1/18/2019	23.7 MB	14.12.25810.0	
	Microsoft Visual C++ 2017 Redistributable (x86) - 14.1	Microsoft Corporation	1/18/2019	20.1 MB	14.12.25810.0	
	Microsoft Visual Studio Installer	Microsoft Corporation	3/6/2019		1.18.1096.130	
	pgAdmin 4 version 4.2	The pgAdmin Development Tea	2/8/2019	195 MB	4.2	
	PostgreSQL 9.3	PostgreSQL Global Developmen	2/8/2019	137 MB	9.3	
	PremiumSoft Navicat Premium 12.1	PremiumSoft CyberTech Ltd.	3/5/2019	203 MB	12.1.16	
	psqIODBC_x64	PostgreSQL Global Developmen	1/8/2019	3.41 MB	09.03.0300	
	Sentinel Runtime	Gemalto	1/8/2019	19.4 MB	7.80.18023.60000	
	Sp SpecifiSuite	Specifi Global LLC	4/9/2019	880 MB	4.0.100	
	🔁 TeamViewer 14	TeamViewer	3/20/2019		14.2.2558	
	Update for Windows 10 for x64-based Systems (KB40	Microsoft Corporation	3/20/2019	1.36 MB	2.56.0.0	
	Visual Studio Community 2017	Microsoft Corporation	3/6/2019		15.9.28307.481	
	VMware Tools	VMware, Inc.	1/18/2019	79.6 MB	10.3.2.9925305	
	Specifi Global LLC Product version: 4.0.10 Help link http://	0 Support li /specifiglobal.coUpdate informati	nk: http://spe on: http://spe	cifiglobal.co cifiglobal.coC	Size: 880 MB Comments: Specifi	

Confirm by clicking on the "Yes" button

Windows Installer	\times
Disinstallare il prodotto?	
Si No	

Specifi will now be uninstalled from your PC but folders and files (created or modified after the installations remain).



You can perform a complete removal of all these elements.

The full removal of all the Specifi folders and files has to be done by a qualified technician. This, to avoid any risks to delete important information from your PC which you will not be able to later retrieve.

The Specifi installation software creates the following folders: C:\Users\[windows_user]\ AppData\Roaming\Specifi Global LLC C:\Users\[windows_user]\ AppData\Local\Specifi_Global_LLC C:\Users\[windows_user]\ AppData\Local\SpecifiGlobal C:\Users\Public\Roaming\SpecifiGlobal

You can delete these folders for a complete uninstallation.

2 In a local installation all the projects, containing drawings and/or offers, are saved in the following folder:

C:\Users\[windows_user]\ Documents\SpecifiProjects

A backup folder is also created for projects deleted through the interface of the Specifi software:

C:\Users\Public\Documents\SpecifiBackup\SpecifiProjects

Warning: this backup folder does not contain files and sub-folders manually deleted by the user.

